



Windows 7 Bluetooth printer configuration guide


1. Click on "Bluetooth " → Add Device.




2. Click on the search to the "Bluetooth Printer" → Next.




3. Click on "Enter the device's pairing code".



4. Enter the pairing code "1234" → Next.




5. Prompted "This device has been successfully added to this computer".




6. Click on "Bluetooth" → Showing Bluetooth device.




7. Click on "Bluetooth Printer" → Properties.




8. At the Properties Click on "Services" → Serial port (SPP) → Apply.




9. Open the Device Manager (Right click-Computer → Properties → Device Manager) → Ports.




10. Click on "Bluetooth" → Port Setting → OK.




11. Click on the "Printer Properties".




12. Choose the "Ports" → COM3 → Apply.



13. Click on "Device Setting" → Print Model → Print as soft font → Apply.



14. Click on "General" → Print Text Page.



15. Print a test page results.

